Additel/LogII Data Logging Software

User Manual

Additel Corporation

2013-3

Contents

Chapter One: Overview	3
1. Introduction	3
2. System Requirements	3
3. Software Installation	3
Chapter Two: Functions	5
1. Automatic Scanning	6
2. Action Scope of Buttons	6
3. Settings	7
4. Logging	9
5. Clear	9
6. Unit	9
7. View	11
8. Data Manager	11

Chapter One: Overview

1. Introduction

Additel/LogII is specially designed to collect real-time data of pressure units under test (UUT). It is a necessary software in pressure data logging.

The features of Additel/LogII:

- It can automatically scan pressure gauges connected to the computer.
- Graphical interface can display the real-time pressure value and draw the curve for UUTS.
- Supports multiple instruments under test at the same time.
- To store pressure value according to the defined time.
- Supports data exporting in 3 formats.
- Multilingual user interface.

2. System Requirements

Hardware Requirements

CPU: Intel Pentium III (At least)Memory: 1GB (At least)Hard Disk free space: 2GB (At least)Hardware must has serial port

Software Requirements

Operating System:

Windows XP/Windows 2003/Windows Vista/Windows7/Windows8

3. Software Installation

First, Open the file Setup.exe to start the installation.

Second, Install driver will detect whether the following components are installed in system or not. If not, they will be installed automatically; otherwise it will be skipped.

- Windows Installer 3.1
- Windows Imaging Component
- Microsoft .NET Framework 4

Third, The Wizard interface will appear as shown in below picture. Users can finish the installation by following this Wizard.



Figure 1-1

When the installation is finished, the following icon will be shown on the desktop. As below picture 1-2.



Figure 1-2

Chapter Two: Functions



Start the software by double-clicking above icon, the main interface will be shown as below.

Figure 2-1

The main interface consists of 5 parts:

No.	Name	Description
1	Toolbar	It includes all the functions.
2	UUTs' list	The list will display all the connected UUTs. It shows the UUTs' information, real-time pressure value, real-time curve and main function buttons.
3	Real-time pressure display area	This area will display the real-time pressure, max pressure, min pressure and average value of selected UUT.
4	Pressure value curve display area	This area shows the whole curve of selected UUT.
5 Status bar		This area shows information like prompt message and software version.

1. Automatic Scanning

Once it starts, the software will automatically scan the connected UUTS without manual operation. And the relevant UUT information frame will be displayed in the UUTs' list area (#2).

The real-time pressure value and curve of selected UUT will be displayed separately in area #3 and #4 too.

If the software cannot detect the connected UUT, please check the following items.

- Please check whether the serial drive or USB to RS232 drive are installed correctly.
- Please make sure the cable is connected tightly with interface.
- If users use USB to RS232 cable to connect with PC, please re-plug the USB port into PC to make sure the cable could work properly.
- Please check whether the UUT is turned on.
- Please check whether the Baud rate of UUT matches the software.
- Please make sure there is no other software of PC occupied the serial port used by UUT.

2. Action Scope of Buttons

The functions of "Log", "Setting", "Clear", "Unit" and "Export" are same with the five buttons on the each frame of UUTs. And they are one to one correlate. As shown in picture 2-2.

The difference is the buttons on the toolbar could control all the connected UUTs, however the buttons on each frame could only control the relevant one.



Figure 2-2

3. Settings



Click the button **Settings** on toolbar, the Settings interface appears as below.

Settings	×
General Format	
Logging Interval	
0 $\stackrel{\frown}{\nabla}$ Hours 0 $\stackrel{\frown}{\nabla}$ Minutes 1.0 $\stackrel{\frown}{\nabla}$ Seconds	
- Logging Duration	
Always Logging O Custom	
0 A Days 0 A Hours 10 Minutes	
Communication	
BaudRate 9600 💌	
OK Cancel	

Figure 2-3

General

• Logging Interval

It means the interval time between 2 stored data.

• Logging Duration

Means the total time of the whole logging process will last. The default value will never stop the logging process, users can decide when to stop it according to requirements. Please set time before logging.

Communication •

The default value of baud rate of serial port is 9600. No need to change it in general.

Format

Chart Style •

To set the display mode of the Chart.

Date Format •

To set the display mode of the Date.



on UUT frame to enter the below window. There is another tab Click the button (Gauge Profile) in the Settings.

Settings
General Format Gauge Profile
Scale
Reading multiplying factor 1.000 (range: 0.900 to 1.100)
Reading offset value 0.000000 👘 bar
Resolution
Number Digits 5
Default
OK Cancel

Figure 2-4

Gauge Profile

• Scale

Reading multiplying factor (range: 0.900 to 1.100). Standard value should be 1.000. If display is 1.500, when we key-in the reading multiplying factor to 1.1. The display will change to read 1.650 (1.500 x 1.100)

Reading offset value. If we offset the reading of 0.123, then all the reading will be minus 0.123 even you off the power and on again. It is different from the zeroing.

• Resolution

Selection of Resolution. It is able to select the decimal point at which position. In the down list, you can select 5 or 6.

4. Logging

Softwae will display the real-time pressure value and the real-time chart. However it has not stored these data yet, users need to click the "start all" under the "log" menu or to click

the button on each frame of UUTs to start storing.

When users want to stop storing data, they can click the "Stop All" under "Log" menu or



buttons on each frame of UUTs.

5. Clear

Users can delete the stored data by clicking button Clear on toolbar or

frame of UUTs. When the deleting operation is finished, it will re-start another logging task automatically.

on each

6. Unit



Engineering Unit			B					
Unit Editor								
Unit Name	Unknown	nsi 🔿	Cancel					
Conversion Factor	1	U poi						
Note: Pressure(Unknown)=Pressure(kPa) * 1								



Users can change the pressure unit by clicking button Pa on each frame of UUTs. If you want to change the current pressure unit , please select the Custom Mode. And in the Custom Mode you can finde the pressure unit which is defined by yourself. The Automatic Mode is checked in system by default.



Figure 2-6

7. View

There are 3 different kinds of view for the interface, Details, List and Classical. The default is Details, as shown in below picture 2-1. Users can switch among them as per requirements by clicking the buttons in the "view" menu.



Figure 2-7

8. Data Manager



1

Click Export button on the toolbar or **Less** buttons on each frame of UUTs to enter

into the data managing window. This window includes the following functions.

• Search

Users can search the stored data by setting time or inputting S/N of UUTs.

• Browse

Users can view the details information of selected data by clicking the "Open" on toolbar or double-click it.

• Export

The recorded data can be exported out as 3 formats, Excel workbook, XML Sheet and CSV Text File.

- Delete records
- Backup, recover or compress database.

💫 Data Manager								x		
	Export Open 💥 Delete 😾 Clear 🟠 Advanced - 🔗 Cancel									
Seek Options										
© Today ○ Week ○ Month ○ All ○ Custom 2012-08-18 □ - 2012-11-16 □ -										
S/N T										
File Format										
	۲	Excel Workbook	© XM	L Sheet	CSV Tex	t File				
1										
	ID	S/N	Model	Range	Number	Start DateTime	End DateTime	Interval(HH:mm:ss.s)	RealUnit	Ma
	1	211155408979	ADT681	(0-60)bar	3	2012-11-16 17:13:34	2012-11-16 17:13:37	00:00:01.0	bar	1.
	2	211155408266	ADT681	(0-60)bar	3	2012-11-16 17:13:34	2012-11-16 17:13:37	00:00:01.0	bar	1.
Þ	3	211155402823	ADT681	(0-60)bar		2012-11-16 17:13:34	2012-11-16 17:13:37	00:00:01.0	bar	1.
	4	211155356788	ADT681	(0-60)bar	4	2012-11-16 17:13:34	2012-11-16 17:13:37	00:00:01.0	bar	1.
	5	211155408979	ADT681	(0-60)bar	22	2012-11-16 17:12:50	2012-11-16 17:13:12	00:00:01.0	bar	1.
	6	211155408266	ADT681	(0-60)bar	23	2012-11-16 17:12:50	2012-11-16 17:13:13	00:00:01.0	bar	1.
	7	211155402823	ADT681	(0-60)bar	23	2012-11-16 17:12:50	2012-11-16 17:13:13	00:00:01.0	bar	1.
	8	211155356788	ADT681	(0-60)bar	23	2012-11-16 17:12:50	2012-11-16 17:13:13	00:00:01.0	bar	1.
	9	211155408979	ADT681	(0-60)bar	16	2012-11-16 17:12:34	2012-11-16 17:12:50	00:00:01.0	bar	1.
	10	211155408266	ADT681	(0-60)bar	16	2012-11-16 17:12:33	2012-11-16 17:12:50	00:00:01.0	bar	1.
	11	211155402823	ADT681	(0-60)bar	17	2012-11-16 17:12:33	2012-11-16 17:12:50	00:00:01.0	bar	1.
	12	211155356788	ADT681	(0-60)bar	17	2012-11-16 17:12:33	2012-11-16 17:12:50	00:00:01.0	bar	1.
۲ () () () () () () () () () (
12	records	found.								

Figure 2-8